

## Common April 2013

### NIM 101



Jaqui Lynch

lynchj@forsythe.com

Presentation can be downloaded from link at bottom of:  
<http://www.circle4.com/papers/common-nim101.pdf>

1

## Agenda

- Introduction
- NIM Resources
- Setup
- Client installs
- Hints and tips

2

## Introduction

- Central point of management for installation and maintenance
- Used for LPARs and standalone servers
- Create golden image and clone LPARs
- Can install from software, golden image or mksysb
- Can use to apply maintenance or add bundles of products
- Can install multiple servers at a time
- Push or pull installs
- Fast – DVD takes about 8 hours, NIM 15 minutes
- Can do alternate disk installs, multibos, NIM clones

3

## NIM environment

- Master
  - NIM server itself
  - Owns and provides the resources necessary to service clients
  - Stores information about clients and resources
  - Stores information about NIM in its database
  - Need to backup NIM database regularly
- Client
  - Machines defined as clients
  - Standalone, diskless, dataless
  - System WPAR machines
- Network
  - Must support NFS
  - If using TCP wrappers will need to unwrap tftp and bootpd on the NIM master
  - At AIX v5.3 NIM no longer requires the r commands (rsh)
  - Use nimsh instead of rsh, etc

4

## NIM Server Setup

- Must be at highest level of AIX that you plan to support
- Should use dedicated resources for Disk and Network
  - Affects ability to restore images if depends on VIO
  - Same applies to TSM server
- Plan for memory (2-4GB is plenty) and core (.5 of a core with 2 VPs)
- Create scalable VG - nimvg on disk to hold NIM resources
  - Do not put NIM resources into rootvg
- Create /nim filesystem in nimvg (JFS2)
- I also create a separate filesystem called /backups for mkysyb images
- Install filesets and any updates from TLs for them
  - bos.sysmgt.nim.master
  - bos.sysmgt.nim.spot
  - bos.sysmgt.nim.client
- Also ensure the following filesets are installed
  - bos.net.tcp.server
  - bos.net.nfs.server
- Use lspp to check they are there

5

## More Setup

- Note – NIM does not like dot in resource names so use \_
- Put AIX DVD in the DVD drive or replace /dev/cd0 below with the directory you have the BFFs from the DVD loaded up to
- Setup NIM
  - nim\_master\_setup -B -a device=/dev/cd0 -a file\_system=/nim -a volume\_group=nimvg
    - Creates /tftpboot
    - Will not take a mkysyb of the NIM server
    - Creates SPOT and lpp\_source resources in /nim
  - Directory Structure:
    - /nim
    - /nim/lpp\_source
    - /nim/images
    - /nim/spot
    - /nim/bosinst\_data
    - /nim/resolv\_conf

6



## NIM on my 7.1 system

```
#lspp -l | grep bos.sysmgt.nim
bos.sysmgt.nim.client 7.1.1.0 COMMITTED Network Install Manager -
bos.sysmgt.nim.master 7.1.1.0 COMMITTED Network Install Manager -
bos.sysmgt.nim.spot 7.1.0.15 COMMITTED Network Install Manager - SPOT
bos.sysmgt.nim.client 7.1.1.0 COMMITTED Network Install Manager -

#df -g /nim
Filesystem GB blocks Free %Used lused %lused Mounted on
/dev/fslv05 165.25 81.51 51% 182982 1% /nim

#ls -al /nim
total 24
drwxr-xr-x 9 root system 256 Aug 26 2011 .
drwxr-xr-x 42 root system 4096 Apr 04 23:41 ..
drwxr-xr-x 2 root system 256 Apr 11 2011 bosinst_data
drwxr-xr-x 2 root system 4096 Nov 28 17:06 images
drwxr-xr-x 2 root system 256 Mar 22 2011 lost+found
drwxr-xr-x 10 root system 256 Nov 28 17:22 lpp_source
drwxr-xr-x 2 root system 256 Apr 18 2011 scripts
drwxr-xr-x 13 root system 4096 Nov 28 17:47 spot
drwxr-xr-x 3 root system 256 Apr 15 2011 spotspot_53tl12sp2
```

7

## NIM Command output after setup (6.1 system)

```
# lspp -l | grep nim
bos.sysmgt.nim.client 6.1.5.2 COMMITTED Network Install Manager -
bos.sysmgt.nim.master 6.1.5.2 COMMITTED Network Install Manager -
bos.sysmgt.nim.spot 6.1.5.1 COMMITTED Network Install Manager - SPOT
bos.sysmgt.nim.client 6.1.5.2 COMMITTED Network Install Manager -

# df -g /nim
Filesystem GB blocks Free %Used lused %lused Mounted on
/dev/lvnm 125.00 56.33 55% 76032 1% /nim

# ls -al /nim
total 16
drwxr-xr-x 8 root system 256 Jan 06 2010 .
drwxr-xr-x 26 root system 4096 Sep 07 11:02 ..
drwxr-xr-x 2 root system 256 Jan 06 2010 bosinst_data
drwxr-xr-x 3 root system 4096 May 05 14:32 images
drwxr-xr-x 2 root system 256 Jan 05 2010 lost+found
drwxr-xr-x 6 root system 256 Apr 29 08:42 lpp_source
drwxr-xr-x 2 root system 256 Jan 06 2010 resolv_conf
drwxr-xr-x 6 root system 256 Apr 29 09:07 spot
```

8

## Check network setup

- # cat /etc/hosts | grep gandalf
- 10.152.10.124 gandalf
- 
- # cat /etc/inetd.conf
- ##
- ## service socket protocol wait/ user server server program
- ## name type nowait program arguments
- ##
- bootps dgram udp wait root /usr/sbin/bootpd bootpd /etc/bootptab
- tftp dgram udp6 SRC nobody /usr/sbin/tftpd tftpd -n
- 
- Do not TCP wrap these
- For security reasons you can comment them out and just uncomment when you want to use them

9

## NIM Resources

- Machines
  - These are the clients
- lpp\_source
  - The lpp\_source (Licensed Program Product source) directory contains the images that AIX uses to load software. These are typically the BFF (backup file format) images that exist on the AIX installation CDs or DVD. Each OS version should have its own lpp\_source. Additionally these should be separated into 32-bit and 64-bit lpp\_source sets.
- SPOT
  - The SPOT (Shared Product Object Tree) is a directory that is created from the lpp\_source. The SPOT is used in a similar fashion to the boot images and installation scripts on the Base installation CD volume 1 for AIX. It may be necessary to create multiple SPOTs depending on the maintenance levels and versions that need to be supported.
- mkysyb
  - The NIM master can use lpp\_source to install an instance or it can install the instance from a mkysyb of either that instance or another one. Once the mkysyb is restored a script can be run automatically to customize the instance .

10

## NIM Resources 1/2

### #ls /nim/lpp\_source

```
lpp_53tl12sp2 lpp_61tl06sp2 lpp_61tl06sp5 lpp_7100tlsp2
lpp_61tl05sp1 lpp_61tl06sp3 lpp_7100tl00sp3 lpp_71tl01sp1
```

### # ls /nim/spot

```
53tl12sp2 spot_61tl05sp1 spot_61tl06sp3 spot_71tl00sp2 spot_71tl01sp1 vio212sp4spot
spot_53tl12sp2 spot_61tl06sp2 spot_61tl06sp5 spot_71tl00sp3 spot_vio
```

### #ls /nim/images

```
aix53.golden.mksysb aix61tl06.mksysb aix7101sp3.mksysb
aix53tl12sp2.golden.mksysb aix61tl06sp5-golden.mksysb aix71tl01sp1-nov2811.mksysb
aix61tl05sp1.mksysb aix71-tl00-sp3.golden.mksysb b740vio1.mksysb
```

### #lspv | grep nimvg

```
hdisk0 00f6934bdeb1713b nimvg active
hdisk5 00f6934be0630676 nimvg active
```

11

## NIM Resources 2/2

### # lsvg nimvg

```
VOLUME GROUP: nimvg VG IDENTIFIER: 00f6934b00004c000000012ee06306b7
VG STATE: active PP SIZE: 256 megabyte(s)
VG PERMISSION: read/write TOTAL PPs: 2234 (571904 megabytes)
MAX LVs: 256 FREE PPs: 32 (8192 megabytes)
LVs: 4 USED PPs: 2202 (563712 megabytes)
OPEN LVs: 4 QUORUM: 2 (Enabled)
TOTAL PVs: 2 VG DESCRIPTORS: 3
STALE PVs: 0 STALE PPs: 0
ACTIVE PVs: 2 AUTO ON: yes
MAX PPs per VG: 32768 MAX PVs: 1024
LTG size (Dynamic): 1024 kilobyte(s) AUTO SYNC: no
HOT SPARE: no BB POLICY: relocatable
MIRROR POOL STRICT: off
PV RESTRICTION: none INFINITE RETRY: no
```

### #lsvg -l nimvg

```
nimvg:
LV NAME TYPE LPs PPs PVs LV STATE MOUNT POINT
loglv00 jfs2log 1 1 1 open/syncd N/A
fslv04 jfs2 920 920 1 open/syncd /software
fslv05 jfs2 661 661 2 open/syncd /nim
fslv06 jfs2 620 620 2 open/syncd /backups
```

12

## NIM Resources

- Scripts
  - Scripts can be set to run during a BOS install to ensure that the resulting instance of the operating system is correctly tailored with any post installation items. These can include security requirements, third-party software installation and other customizations related to additional paging or dump space.
- bosinst\_data
  - This is a file, not a directory, and it contains the necessary information to allow the installation to take place without manual intervention. It is used to define defaults such as default disk drive, type of installation and so on.
- image\_data
  - This is also a file and contains operating system image information related to file systems, mirroring, etc.
- installp\_bundles
  - These are files that list additional software to be loaded after AIX is installed. This can be useful when setting up groups of servers. As an example one bundle may be for DB2 servers while another may be for web servers. Once the Operating System is installed you simply select the post install bundle and apply it.

13

## Client Machine Information

- Hardware Platform Type – default is chrp, older rs6k or rspc not supported
- Kernel to use for Network Boot - set to mp (AIX 5.3 discontinued shipment of up kernel – 5.3 ships only MP 32bit or MP 64bit, v6 and higher are MP 64bit only)
- Cable Type - most likely tp, not bnc or dix – N/A for virtual Ethernet
- Network Adapter Hardware Address - optional field
- More flexible to specify IP parameters on SMS menus during nim client boot.
- You must specify IP parameters if nim client and nim master are on different IP subnets
- Network Adapter Logical Device name - optional field - note this is an adapter name (entx) not an interface name (not enx or etx)
- Machines can register themselves. A running AIX instance (machine or LPAR) can become a client, can define itself to this server, by doing a smitty niminit.

14

## List resources

```
• # lsnim
• master          machines  master
• boot            resources boot
• nim_script      resources nim_script
• master_net     networks  ent
• 7100-00bid_ow  resources bosinst_data
• lpp_61t106sp3  resources lpp_source
• spot_61t106sp3 resources spot
• mkysyb_aix61t106sp3 resources mkysyb
• basic_res_grp  groups   res_group
• lpp_71t100sp3  resources lpp_source
• spot_t100sp3   resources spot
• mkysyb_71t100sp3 resources mkysyb
• mkysyb_53t112sp2 resources mkysyb
• lpp_53t112sp2  resources lpp_source
• spot_53t112sp2 resources spot
• ent-Network1  networks ent
• b750nr1        machines standalone
• changepw       resources script
• viomkysyb     resources mkysyb
• b750ns1        machines standalone
• lpp_71t101sp1  resources lpp_source
• spot_71t101sp1 resources spot
• mkysyb_71t101sp1 resources mkysyb
```

15

## List resources

```
• #showmount -e
• export list for nimsrvr:
• /export/nim/scripts/b750nr1.script  b750nr1
• /software                          b750nr1
• /backups                            b750nr1
• /nim/lpp_source/lpp_7100t100sp3    b750r1
• /nim/spot/spot_71t100sp3/spot_t100sp3/usr b750nr1

• #lsnim -l b750nr1
• b750nr1:
• class          = machines
• type           = standalone
• connect        = nimsh
• platform       = chrp
• netboot_kernel = 64
• if1            = master_net b750nr1 0
• cable_type1    = N/A
• Cstate         = Base Operating System installation is being performed
• prev_state     = BOS installation has been enabled
• Mstate         = in the process of booting
• info           = prompting_for_data_at_console
• boot           = boot
• lpp_source     = lpp_71t100sp3
• nim_script     = nim_script
• spot          = spot_t100sp3
• cpuid         = 00F693484C00
• control        = master
• Cstate_result = success
```

16



## Update resources

- Put update CD in or change into fixes directory
- Update SPOT and lpp\_source
  - smitty nim
  - Perform nim administration tasks
  - Manage resources
  - Perform operations on resources
  - Select the SPOT
  - Select update\_all
  - Point it to the update CD or directory
- OR
- `nim -o define -t lpp_source -a server=master -a location=/nim/lpp_source/lpp_71tl01sp1 -a source=/software/aixv7/aix71-base lpp_71tl01sp1`
- `nim -o update -a packages=all -a source=/software/aixv7/aixv7-tl01-sp1 lpp_71tl01sp1`
- `nim -o define -t spot -a server=master -a location=/nim/spot -a source=lpp_71tl01sp1 spot_71tl01sp1`
- `nim -o check spot_71tl01sp1`
- `nim -o check lpp_71tl01sp1`
- `nim -o reset -a force=yes b740nl1`

17

## Setup a client to restore from a mksysb

- Make sure gandalf (client) is in /etc/hosts or in DNS and that the name can be resolved
- Create the client (gandalf) machine to nim as a machine object
- The first step is to define gandalf as a client machine
  - smitty nim, perform admin tasks, manage machines
  - Define gandalf as a machine
  - Select 64 as kernel, nimsh as shell, N/A as network i/face

18

## Image\_data

- Template is /usr/lpp/bosinst/image.template
- Copy and modify
- Specify things like
  - logical volume policy
  - SHRINK=no
  - EXACT\_FIT=no
  - lv\_data: (an lv\_data stanza for each logical volume in rootvg)
    - COPIES= 1 ( or 2, 3 to mirror. make sure you have enough target disk stanzas in the bosinst\_data resource)
    - LPs= nn (the number of logical partitions)
    - PP= nn (if mirroring, this is an exact 2x or 3x of LPs)
- IF you don't specify an image\_data resource, NIM will use the file embedded in the mksysb image.
- Typical use of a "side" image.data file is when mksysb is mirrored, but the new install is to be nonmirrored, or vice-versa.

19

## Setup mksysb as a resource

smitty nim

Perform nim administrative tasks

Manage resources

Define a resource

Select mksysb resource and then fill in the following fields

name = aix61tl2sp2\_mksysb

server = master

location = /nim/images/aix61tl2sp2-golden.mksysb

nim -o define -t mksysb -a server=master -a

location=/nim/images/aix71tl01sp1-nov2811.mksysb mksysb\_71tl01sp1

20

## Tell NIM to use the mksysb for this machine

```
smitty nim_bosinst
  Select gandalf
  install source = aixtl2sp2_mksysb
  select mksysb and spot as resources (also select the lpp)
  Select yes to accept licenses
  Select no to initiate now
```

Initiate now = no means this is a pull resource and must be initiated at the client

```
nim -o allocate -a spot=spot_61tl05 -a lpp_source=61tl05_lpp -a
mksysb=mksysb_61tl05 p6datst1
```

```
nim -o bos_inst -a source=mksysb -a accept_licenses=yes -a boot_client=no
-a installp_flags='-agX' p6datst1
```

21

## Tell NIM to use the mksysb for this machine

```
File Edit View Window Help
Quick Connect Profiles
Install the Base Operating System on Standalone Clients
Type or select values in entry fields.
Press Enter AFTER making all desired changes.

[ ] [Entry Fields]
* Installation Target p6db53a
* Installation Type mksysb
* SPOT spot_61tl05
LPP_SOURCE 61tl05_lpp
MKSYSB mksysb_61tl05

BOSINST_DATA to use during installation 6100-04bid 0w
IMAGE_DATA to use during installation {}
RESOLV_CONF to use for network configuration {}
Customization SCRIPT to run after installation {}
Customization FB Script to run at first reboot {}
ACCEPT new license agreements? yes
Remain NIM client after install? yes
PRESERVE NIM definitions for resources on
this target? yes

FORCE PUSH the installation? no

Initiate reboot and installation now? no
-OR-
Set bootlist for installation at the
next reboot? no

Additional BUNDLES to install {}
-OR-
Additional FILESETS to install {}
(bundle will be ignored)
(MORE...22)

F1=Help F2=Refresh F3=Cancel F4=List
Esc+5=Reset Esc+6=Command Esc+7=Edit Esc+8=Image
Esc+9=Shell Esc+0=Exit Enter=Do

Connected to p6danm SSH2 - aes128-cbc - hmac-md5 - none 131x38
```

22

## List resources

- # lsrim -l gandalf
- gandalf:
  - class = machines
  - type = standalone
  - connect = nimsh
  - platform = chrp
  - netboot\_kernel = mp
  - if1 = master\_net gandalf 0
  - cable\_type1 = N/A
  - Cstate = ready for a NIM operation
  - prev\_state = not running
  - Mstate = not running
  - lpp\_source = 61tl05\_lpp
  - mkysyb = mkysyb\_61tl05
  - spot = spot\_61tl05
  - cpuid = 00C20AE54C00
  - control = master
  - Cstate\_result = failure

23

## Checks

- showmount -e
  - /nim/lpp\_source/61tl05\_lpp gandalf
  - /nim/spot/spot\_61tl05/spot\_61tl05/usr gandalf
  - /nim/images/aix61-tl05sp1-golden.mkysyb gandalf
- # cat /etc/bootptab
- gandalf:bf=/tftpboot/gandalf:ip=10.152.10.124:ht=ethernet:sa=10.152.10.203:sm=255.255.255.0:

24

## Checks

- # ls -al /tftpboot
- lrwxrwxrwx 1 root system 18 May 14 16:14 10.152.10.124 -> /tftpboot/gandalf
- lrwxrwxrwx 1 root system 18 May 14 16:14 10.152.10.124.boot -> /tftpboot/gandalf
- lrwxrwxrwx 1 root system 23 May 14 16:14 10.152.10.124.info -> /tftpboot/gandalf.info
- lrwxrwxrwx 1 root system 28 May 14 16:14 10.152.10.124.iplrecord -> /tftpboot/gandalf.iplrecord
- lrwxrwxrwx 1 root system 33 May 14 16:14 gandalf -> /tftpboot/spot\_61tl05.chrp.64.ent
- -rw-r--r-- 1 root system 1156 May 14 16:14 gandalf.info
- lrwxrwxrwx 1 root system 35 May 14 16:14 gandalf.iplrecord -> /tftpboot/spot\_61tl05.iplrecord.ent
- -rw-r--r-- 1 root system 16958976 Apr 29 12:52 spot\_61tl05.chrp.64.ent
- -rw-r--r-- 1 root system 512 Apr 29 12:52 spot\_61tl05.iplrecord.ent
- -rw-r--r-- 1 root system 16752640 Mar 16 2010 spot\_aix61tl04sp3.chrp.64.ent
- -rw-r--r-- 1 root system 512 Mar 16 2010
- 

25

## Useful NIM commands

- Recover missing simages if needs be:
- nim -o update -a recover=yes -a source=/software/aixv7/aix71-base lpp\_71tl01sp1
- ALLOCATIONS
- nim -o deallocate -a spot=spot\_71tl01sp1 -a lpp\_source=lpp\_71tl01sp1 -a mkysb=mkysb\_71tl01sp1 b740nl1
- nim -o allocate -a spot=spot\_71tl01sp1 -a lpp\_source=lpp\_71tl01sp1 -a mkysb=mkysb\_71tl01sp1 b740nl1
- nim -o bos\_inst -a source=mkysb -a accept\_licenses=yes -a boot\_client=no -a installp\_flags='-agX' b740nl1
- OTHER
- To add the bos.games 5.2.0.0 and bos.terminfo filesets to lpp\_source1, type:
- nim -o update -a packages="bos.games 5.2.0.0 bos.terminfo" \
- -a source=/dev/cd0 lpp\_source1
- To remove bos.games from lpp\_source1, type:
- nim -o update -a rm\_images=yes -a packages="bos.games" lpp\_source1

26

## Backout

- If you have a machine enabled for install, and need to back out...
  - `nim -o reset -a force=yes <nimclienthostname>`
  - `nim -Fo deallocate -a subclass=all <nimclienthostname>`
  - `nim -o change -a cpuid="" <nimclienthostname>`

27

## Start the install from the client

- Boot client into SMS mode either from the HMC or the server

Select 2 for setup remote IPL

Select 1 for first ethernet

Select 1 for IPV4

Select 1 for bootp

Select 1 for IP parameters

1 - client - 10.0.1.5

Use the client IP here

2 - server - 10.0.1.9

Use the NIM server IP here

3 - Gateway - 10.0.1.1

You may need to leave this as 0.0.0.0

4 - Subnet - 255.255.255.0

Esc

Select 2 for adapter config

2 spanning tree - ensure it is disabled (this can speed things up)

ESC

3 - protocol - set it to standard

ESC and ESC

3 Ping test then 1 to execute ping test

If the ping test is successful return to main menu

Select 5 - boot options

1 select boot device

6 select network

1 bootp

1 select first ethernet

2 normal mode boot

1 yes I want to exit

28

## Next steps

- LPAR/Server should boot and you should see tftp start up
- After around 30,000 packets the console prompt should appear
  - F1 and enter for console
  - 1 for english during install
  - An error message that "all LVs are being created exactly as they were but the disks are not the same" may appear. Unless there is a reason not to, go ahead and:
    - Choose 1 to continue with install
  - 2 Check install settings
  - 
  - Make sure that only 1 disk is chosen here and that it is the correct one for rootvg:
    - Choose hdisk0
    - Use maps for installation – I tend to choose no
    - Check that importvgs defaults to n
    - 0 to continue with choices
- Note make sure the mksysb you are using is not of a mirrored system – if it is mirrored then you will need to provide 2 disks to restore to
- After the system reboots you can import volume groups, remirror rootvg and perform further tailoring

29

## Continuing on

- After reboot install should start
- Monitor using lsnim -l lparname
- This will show you how far it has gone

30

## Useful commands

- `lsnim`
- `lsnim -l lparname`
- `nim -o reset -a force=yes clientnode`
- `nim -Fo deallocate -a subclass=all clientnode`
- `nim -o change -a cpuid="" clientnode`
- `bootlist -m normal -o` (check bootlist)
- `arp` and `ping`
- `oslevel -s`
- `Instfix`
- `showmount -e`
- `ls -al /tftpboot`

31

## Useful commands on master

- `# lsnim -l mksysb_61tl05`
- `mksysb_61tl05:`
  - `class = resources`
  - `type = mksysb`
  - `Rstate = ready for use`
  - `prev_state = unavailable for use`
  - `location = /nim/images/aix61-tl05sp1-golden.mksysb`
  - `version = 6`
  - `release = 1`
  - `mod = 5`
  - `oslevel_r = 6100-05`
  - `alloc_count = 2`
  - `server = master`
  - `creation_date = Thu Apr 29 09:35:47 2010`

32



## Useful commands on master

- # lsnim -l 61tl05\_lpp
- 61tl05\_lpp:
  - class = resources
  - type = lpp\_source
  - comments = AIX 61 tl05 sp1 lpp
  - arch = power
  - Rstate = ready for use
  - prev\_state = unavailable for use
  - location = /nim/lpp\_source/61tl05\_lpp
  - simages = yes
  - alloc\_count = 2
  - server = master

33

## Useful commands on master

- # lsnim -l spot\_61tl05
- spot\_61tl05:
  - class = resources
  - type = spot
  - plat\_defined = chrp
  - arch = power
  - bos\_license = yes
  - Rstate = ready for use
  - prev\_state = verification is being performed
  - location = /nim/spot/spot\_61tl05/spot\_61tl05/usr
  - version = 6
  - release = 1
  - mod = 5
  - oslevel\_r = 6100-05
  - alloc\_count = 2
  - server = master
  - if\_supported = chrp.64 ent
  - Rstate\_result = success

34

## Useful commands on master

- # ls -al /etc/niminfo
- -rw-r--r-- 1 root system 164 Jan 06 2010 /etc/niminfo
- # cat /etc/niminfo
- # nimconfig
- export NIM\_NAME=master
- export NIM\_CONFIGURATION=master
- export NIM\_MASTER\_PORT=1058
- export NIM\_REGISTRATION\_PORT=1059
- export NIM\_MASTER\_HOSTNAME=pnimmstr

35

## Useful commands on master

- # ls -al /etc/objrepos/nim\*
- -rw-rw-r-- 1 root system 24576 Sep 28 10:20 /etc/objrepos/nim\_attr
- -rw-rw-r-- 1 root system 36864 Sep 28 10:20 /etc/objrepos/nim\_attr.vc
- -rw-rw-r-- 1 root system 4096 Sep 28 10:20 /etc/objrepos/nim\_object
- -rw-rw-r-- 1 root system 8192 Sep 28 10:20 /etc/objrepos/nim\_object.vc
- -r-xr-x--- 1 root system 28672 Sep 06 09:48 /etc/objrepos/nim\_pdatr
- -r-xr-x--- 1 root system 36864 Sep 06 09:48 /etc/objrepos/nim\_pdatr.vc

36

## Backing up and restoring NIM

- Save the following NIM files on the master
  - /etc/niminfo
  - /etc/objrepos/nim\_attr
  - /etc/objrepos/nim\_attr.vc
  - /etc/objrepos/nim\_object
  - /etc/objrepos/nim\_object.vc
- You can restore the NIM database and activate the NIM master using the Web-based System Manager, SMIT, or the command line.
- Restore the files saved in Backing up the NIM database.

37

## Recovering /etc/niminfo

- /etc/niminfo is required on master and running NIM clients to run NIM operations and commands
- You can rebuild it on the master:
  - `nimconfig -rTo`
- You can rebuild it from a running NIM client:
  - `niminit -a master_port= PortNumber -a master= MasterHostName -a name= ClientMachineObjectName`

38

## /etc/niminfo on the client

- export NIM\_NAME=gandalf
- export NIM\_HOSTNAME=gandalf
- export NIM\_CONFIGURATION=standalone
- export NIM\_MASTER\_HOSTNAME=pnimmstr
- export NIM\_MASTER\_PORT=1058
- export NIM\_REGISTRATION\_PORT=1059
- export NIM\_SHELL="nimsh"
- export NIM\_MASTERID=00C20AE54C00
- export RC\_CONFIG=rc.bos\_inst
- export NIM\_BOSINST\_RECOVER=" ../SPOT/usr/lpp/bos.sysmgmt/nim/methods/c\_bosinst\_env -a hostname=gandalf"
- export SPOT=pnimmstr:/nim/spot/spot\_61tl05/spot\_61tl05/usr
- export NIM\_CUSTOM=" ../SPOT/usr/lpp/bos.sysmgmt/nim/methods/c\_script -a location=pnimmstr:/export/nim/scripts/gandalf.script"
- export NIM\_BOS\_IMAGE=/NIM\_BOS\_IMAGE
- export NIM\_BOS\_FORMAT=mksysb
- export NIM\_HOSTS=" 127.0.0.1:loopback:localhost 10.152.10.124:gandalf 10.152.10.203:pnimmstr "
- export NIM\_MOUNTS=" pnimmstr:/nim/lpp\_source/61tl05\_lpp:/SPOT/usr/sys/inst.images:dir pnimmstr:/nim/images/aix61-tl05sp1-golden.mksysb:/NIM\_BOS\_IMAGE:file "
- export ROUTES=" default:0:10.152.10.1 "

39



## Migrations and Updates

### Migration

Changes version or release

### Update

Preserves version and release  
Basically changes a TL or SP

Both migrations and updates can use alternate copies of rootvg if there is an unused disk available

After changes, boot from altinst\_rootvg and test

Migrate or update NIM Master first  
Then update LPP\_SOURCE and SPOT

Use nimadm for migrations, to install a down level mksysb and then migrate it or to install a new golden image

Use nim\_alt\_clone with update\_all to update a TL or SP  
With multibos the standby copy of AIX can be on the same physical disk as the current rootvg

40

**nimadm (Network Install Manager Alternate Disk Migration) command**

Utility that allows the system administrator to:

Create a copy of rootvg to a free disk (or disks) and simultaneously migrate it to a new version or release level of AIX.

Using a copy of rootvg, create a new NIM mksysb resource that has been migrated to a new version or release level of AIX.

Using a NIM mksysb resource, create a new NIM mksysb resource that has been migrated to a new version or release level of AIX.

Using a NIM mksysb resource, restore to a free disk (or disks) and simultaneously migrate to a new version or release level of AIX.

**Update within the same version/release (i.e update a TL or SP)**

Build the lpp\_source at the desired level with simages-yes  
Update NIM master from this lpp\_source and reboot master

**On client**

Unmirror rootvg and cleanup (chpv -c and reducevg)  
bosboot -a and bootlist -m

**Master**

smitty nim\_alt\_clone  
Specify target client and target disks  
Setc FIXES to install to "update\_all"  
Point to lpp\_source from above and accept licenses

The clone and update will take place on altinst\_rootvg while still running on rootvg

Boot from altinst\_rootvg and test

Either reboot from old rootvg or make this the production one

Creates, updates, and manages multiple versions of the Base Operating System (BOS) on a rootvg.

The multibos command allows the root level administrator to create multiple instances of AIX(R) on the same rootvg.

The multibos setup operation creates a standby Base Operating System (BOS) that boots from a distinct boot logical volume (BLV).

This creates two bootable sets of BOS on a given rootvg and the administrator can boot from either instance of BOS by specifying the respective BLV as an argument to the bootlist command or using system firmware boot operations.

Two bootable instances of BOS can be simultaneously maintained.

- [http://pic.dhe.ibm.com/infocenter/aix/v7r1/topic/com.ibm.aix.install/doc/insgdrf/HT\\_insgdrf\\_altdiskinstall\\_clone.htm](http://pic.dhe.ibm.com/infocenter/aix/v7r1/topic/com.ibm.aix.install/doc/insgdrf/HT_insgdrf_altdiskinstall_clone.htm)
- Make sure you have a spare hard disk or LUN
- Install bos.alt\_disk\_install.rte and update it
- Create a bundle to install to the new disk and any custom scripts
  - Or take a mkysyb of the system to a file
- Clone rootvg using smitty alt\_clone
- lspv now shows a disk as rootvg and one as altinst\_rootvg
- Check your bootlist as the alt disk install process changes it
  - bootlist -m normal -o
- Correct the bootlist back to normal until you are ready
- Now you can use smitty alt\_disk\_install to do the upgrades to then new hard drive
- When happy with the upgrade you update the bootlist and reboot on the new image

## Commands to look at:

```
alt_disk_copy
alt_disk_install
alt_disk_mksysb
alt_rootvg_op
```

```
#
# lspv
hdisk0      00f6934c642af030      rootvg      active
hdisk1      none                          None
# lsdev -Ccdisk
hdisk0 Available Virtual SCSI Disk Drive
hdisk1 Available Virtual SCSI Disk Drive
#
# lspp -l | grep bos.alt
bos.alt_disk_install.boot_images
bos.alt_disk_install.rte 7.1.0.15 COMMITTED Alternate Disk Installation
bos.alt_disk_install.rte 7.1.0.15 COMMITTED Alternate Disk Installation
```

```
Alternate Disk Installation
Move cursor to desired item and press Enter.
Install mksysb on an Alternate Disk
Clone the rootvg to an Alternate Disk
MMX Alternate Disk Migration

F1=Help      F2=Refresh   F3=Cancel    F8=Image
F9=Shell     F10=Exit    Enter=Do
```

```
Install mksysb on an Alternate Disk
Type or select values in entry fields.
Press Enter AFTER making all desired changes.

* Target Disk(s) to install
* Device or image name
Phase to execute
image.data file
Customization script
Set bootlist to boot from this disk
on next reboot?
Reboot when complete?
Verbose output?
Debug output?
resolv.conf file

[Entry Fields]
[hdisk1] +
[/usr/local/backups/b7] +
all +
[] /
no +
no +
yes +
no +
[] /

F1=Help      F2=Refresh   F3=Cancel    F4=List
Esc+5=Reset  F6=Command   F7=Edit      F8=Image
F9=Shell     F10=Exit    Enter=Do
```

```

COMMAND STATUS
Command: running      stdout: yes      stderr: no

Before command completion, additional instructions may appear below.

[MORE...6]
Restoring /image.data from mksysb image.
Checking disk sizes.
Creating cloned rootvg volume group and associated logical volumes.
Creating logical volume alt_hd5.
Creating logical volume alt_hd6.
Creating logical volume alt_hd8.
Creating logical volume alt_hd4.
Creating logical volume alt_hd2.
Creating logical volume alt_hd9var.
Creating logical volume alt_hd3.
Creating logical volume alt_hd1.
Creating logical volume alt_hd10opt.
Creating logical volume alt_hd11admin.
Creating logical volume alt_lg_dump1v.
█
[BOTTOM]

```

**Plus many more as it restores from the mksysb image**

47

### Now we see:

```

# lspv
hdisk0      00f6934c642af030      rootvg      active
hdisk1      00f6934c75816830      altinst_rootvg active

```

```

# bootlist -m normal -o
hdisk0 blv=hd5 pathid=0

```

- Phase 1** Creates the **altinst\_rootvg** volume group, the **alt\_** "logical volumes", the **/alt\_inst** file systems, and restores the mksysb or rootvg data.
- Phase 2** Runs any specified customization script, installs updates, new filesets, fixes or bundles (cloning only), copies a **resolv.conf** file if specified, and copies files over to remain a NIM client if specified.
- Phase 3** Unmounts the **/alt\_inst** file systems, renames the file systems and logical volumes, removes the **alt\_ logical** volumes, names ODM and varies off the altinst\_rootvg. It sets the bootlist and reboots if specified.

48



```
# lspv -l hdisk0
hdisk0:
LV NAME      LPs  PPs  DISTRIBUTION  MOUNT POINT
hd8           1    1    00..00..01..00..00  N/A
hd6           64   64   00..64..00..00..00  N/A
hd2           80   80   00..00..80..00..00  /usr
hd4           10   10   00..00..10..00..00  /
hd3           48   48   00..00..48..00..00  /tmp
hd9var        12   12   00..00..12..00..00  /var
hd10opt       32   32   00..32..00..00..00  /opt
hd1           4    4    00..00..04..00..00  /home
hd5           1    1    01..00..00..00..00  N/A
lg_dumpplv2  16   16   00..16..00..00..00  N/A
fslv00        80   80   80..00..00..00..00  /usr/local
fslv01        16   16   00..16..00..00..00  /usr/local/logs
lg_dumpplv    16   16   00..16..00..00..00  N/A
livedump      4    4    00..04..00..00..00  /var/adm/ras/livedump
hd11admin     4    4    00..00..04..00..00  /admin

# lspv -l hdisk1
hdisk1:
LV NAME      LPs  PPs  DISTRIBUTION  MOUNT POINT
alt_hd10opt  32   32   00..32..00..00..00  /alt_inst/opt
alt_hd1       4    4    00..00..04..00..00  /alt_inst/home
alt_hd3       48   48   00..00..48..00..00  /alt_inst/tmp
alt_hd9var    12   12   00..00..12..00..00  /alt_inst/var
alt_hd2       80   80   00..00..80..00..00  /alt_inst/usr
alt_hd4       10   10   00..00..10..00..00  /alt_inst
alt_hd8       1    1    00..00..01..00..00  N/A
alt_hd6       64   64   00..64..00..00..00  N/A
alt_hd5       1    1    01..00..00..00..00  N/A
alt_lg_dumpplv 16   16   00..16..00..00..00  N/A
alt_hd11admin 4    4    00..00..04..00..00  /alt_inst/admin
alt_lg_dumpplv2 16   16   00..16..00..00..00  N/A
alt_fslv01    16   16   00..16..00..00..00  /alt_inst/usr/local/logs
alt_fslv00    80   80   80..00..00..00..00  /alt_inst/usr/local
alt_livedump  4    4    00..04..00..00..00  /alt_inst/var/adm/ras/livedump
```

You can display the above during the mksysb clone  
 At the end altinst\_rootvg is varied offline and these (the alt ones) are all unmounted

```
You can wake up the altinst_rootvg to mount the filesystems and
put it back to sleep:

# alt_disk_install -W hdisk1
-----+
ATTENTION: calling new module /usr/sbin/alt_rootvg_op. Please
see the
alt_rootvg_op man page and documentation for more details.
Executing command: /usr/sbin/alt_rootvg_op -W -d hdisk1
-----+
Waking up altinst_rootvg volume group ...

# lspv
hdisk0 00f6934c642af030 rootvg active
hdisk1 00f6934c75816830 altinst_rootvg active

Back to sleep
# alt_disk_install -S hdisk1
-----+
ATTENTION: calling new module /usr/sbin/alt_rootvg_op. Please
see the
alt_rootvg_op man page and documentation for more details.
Executing command: /usr/sbin/alt_rootvg_op -S hdisk1
-----+
Putting volume group altinst_rootvg to sleep ...
forced unmount of /alt_inst/var/adm/ras/livedump
forced unmount of /alt_inst/var/adm/ras/livedump
forced unmount of /alt_inst/var
forced unmount of /alt_inst/var
forced unmount of /alt_inst/usr/local/logs
forced unmount of /alt_inst/usr/local/logs
forced unmount of /alt_inst/usr/local
forced unmount of /alt_inst/usr/local
forced unmount of /alt_inst/usr
forced unmount of /alt_inst/usr
forced unmount of /alt_inst/tmp
forced unmount of /alt_inst/tmp
forced unmount of /alt_inst/opt
forced unmount of /alt_inst/opt
forced unmount of /alt_inst/home
forced unmount of /alt_inst/home
forced unmount of /alt_inst/admin
forced unmount of /alt_inst/admin
forced unmount of /alt_inst
forced unmount of /alt_inst
Fixing LV control blocks...
Fixing file system superblocks...

# lspv
hdisk0 00f6934c642af030 rootvg active
hdisk1 00f6934c75816830 altinst_rootvg
```

```
# df -g
Filesystem      GB blocks  Free %Used  lused %lused Mounted on
/dev/hd4        0.62      0.41 35%    10330 10%    /
/dev/hd2        5.00      2.37 53%    62100 11%    /usr
/dev/hd9var     0.75      0.47 38%    5785  5%     /var
/dev/hd3        3.00      3.00 1%      72    1%    /tmp
/dev/hd1        0.25      0.25 1%      11    1%    /home
/dev/hd11admin  0.25      0.25 1%      5     1%    /admin
/proc           -         -    -      -     -     /proc
/dev/hd10opt    2.00      1.41 30%    13901 5%     /opt
/dev/livedump   0.25      0.25 1%      4     1%    /var/adm/ras/livedump
/dev/fslv00    5.00      4.93 2%      231   1%    /usr/local
/dev/fslv01    1.00      0.98 2%      39    1%    /usr/local/logs

/dev/alt_hd4    0.62      0.53 1%      13    1%    /alt_inst
/dev/alt_hd11admin 0.25      0.25 1%      5     1%    /alt_inst/admin
/dev/alt_hd1    0.25      0.25 1%      11    1%    /alt_inst/home
/dev/alt_hd10opt 2.00      1.41 30%    13900 5%     /alt_inst/opt
/dev/alt_hd3    3.00      3.00 1%      61    1%    /alt_inst/tmp
/dev/alt_hd2    5.00      2.37 53%    62100 11%    /alt_inst/usr
/dev/alt_fslv00 5.00      4.93 2%      230   1%    /alt_inst/usr/local
/dev/alt_fslv01 1.00      0.98 2%      39    1%    /alt_inst/usr/local/logs
/dev/alt_hd9var 0.75      0.47 38%    5761  5%     /alt_inst/var
/dev/alt_livedump 0.25      0.25 1%      4     1%    /alt_inst/var/adm/ras/livedump
```

```
alt_disk_copy -d hdisk1 -F 5300-01_AIX_ML -l /updates
```

The above copies the current 5300-00 rootvg to hdisk1  
 It applies the updates from /updates to bring the cloned rootvg to 5300-01  
 It also sets the bootlist to boot from hdisk1

Allows you to copy the running system and apply maintenance in one step

After reboot the old rootvg will be named old\_rootvg

Use alt\_rootvg\_op to remove it later

Use bootlist to go back if needs be

## VIOS and NIM

- Add VIOS partition as a client
- Copy the VIOS mksysb image from the CD to your NIM master
  - On VIOS 2.2 media there are 3 images now – the 3<sup>rd</sup> is on DVD 2
  - Copy all 3 images individually to a directory and then use cat to combine them
  - `cat /export/mksysb/vios2.2/mksysb_image  
/export/mksysb/vios2.2/mksysb_image2  
/export/mksysb/vios2.2/mksysb_image3 >/export/mksysb/nim_vios2.2mksysb`
- Define mksysb resource to NIM master
- Define spot on NIM master
  - The source for the SPOT will be the combined mksysb
- Copy the bosinst.data from the DVD and create a viosbosinst resource
- You can now use bos\_inst to do a mksysb install once the partition profile is defined
- <http://www-01.ibm.com/support/docview.wss?uid=isg3T1011386>

53

## Backing up VIOS

- Use viosbr to backup user defined virtual resources on the VIO
- Make sure to save that backup in rootvg
  - `viosbr -backup -file /tmp/viosabkupbr`
  - You can also use viosbr to view or restore
  - <http://publib.boulder.ibm.com/infocenter/systems/scope/hw/topic/p7hcg/viosbr.htm>
- Mount NFS filesystem to backup to (in my case /backups)
- `mkdir /backups/viosa`
- Then as padmin:
  - `backupios -file /backups/viosa`
  - The above creates a nim\_resources.tar package in that directory and it can be used to clone VIO servers
- You can also back it up as a mksysb file that is easy to restore from the NIM server
- `backupios -file /backups/viosa.mksysb -mksysb`

54

- How to install AIX 5L (look for EZNIM)
  - <http://www.ibm.com/developerworks/aix/library/au-install-aix.html>
- SG24-7296 – NIM from A-Z in AIX 5L Redbook – 30 May 2007
  - <http://www.redbooks.ibm.com/redbooks/pdfs/sg247296.pdf>
- The Power of Network Install Manager
  - [http://www.ibm.com/developerworks/aix/library/au-nim/index.html?S\\_TACT=105AGX20](http://www.ibm.com/developerworks/aix/library/au-nim/index.html?S_TACT=105AGX20)
- Simplifying with NIM – article from IBM Systems Magazine 2006
  - <http://www.circle4.com/jaqui/eserver/aixtra-FebMar06-SimplifyingwithNIM.pdf>
- NIM Concepts
  - [http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/nim\\_concepts.htm](http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/nim_concepts.htm)
- Backing up the NIM Database
  - [http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/adv\\_config\\_backup\\_db\\_cmd\\_line.htm](http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/adv_config_backup_db_cmd_line.htm)
- AIX v6.1 NIM Pages
  - [http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/basic\\_config.htm](http://publib.boulder.ibm.com/infocenter/aix/v6r1/topic/com.ibm.aix.install/doc/insgdrf/basic_config.htm)



Send questions to [lynchj@forsythe.com](mailto:lynchj@forsythe.com)

Handout is at:  
<http://www.circle4.com/papers/common-nim101.pdf>

Movies are at:  
<http://www.circle4.com/movies>